

---

# **pyastroimageview Documentation**

***Release 0.0.1***

**Michael Fulbright**

**Nov 02, 2020**



**CONTENTS:**

<b>1</b>	<b>Introduction</b>	<b>1</b>
1.1	What is Pyastroimageview? . . . . .	1
<b>2</b>	<b>Pyastroimageview RPC API Documentation</b>	<b>3</b>
2.1	Format . . . . .	3
2.2	Supported Methods . . . . .	4
<b>3</b>	<b>Indices and tables</b>	<b>9</b>



## INTRODUCTION

### 1.1 What is Pyastroimageview?

Pyastroimageview is an image acquisition program that allows taking images with a supported astronomy hardware (via ASCOM or INDI) including:

- cameras
- mounts
- focusers
- filter wheels

Pyastroimageview can take an image sequence and in addition pyastroimageview will control PHD2 to cause dither events while taking an image sequence.

Pyastroimageview also has an JSON-RPC-like API that allows it to act as a hub for hardware like cameras which do not always support multiple clients.



## PYASTROIMAGEVIEW RPC API DOCUMENTATION

Pyastroimageview supports a JSON-RPC-like API for clients to take images, etc.

### 2.1 Format

The format of an RPC request is:

```
{ 'method' : <method>,  
  'id' : <request_id>,  
  'params' : <params>  
}  
where:  
  <method> : String name of API method being requested  
  <request_id> : Request id number - should be incremented for each request and not  
  ↳ reused  
  <params> : JSON dictionary of parameters required for request
```

The format of a response is:

```
{ 'jsonrpc' : '2.0',  
  'id' : <request_id>,  
  'result' : <result>  
}  
where:  
  <request_id> : Request id number from the request which produced this result  
  <result> : JSON dictionary of result of request
```

If an error occurred instead the response will be:

```
{ 'jsonrpc' : '2.0',  
  'id' : <request_id>,  
  'error' : { 'code' : <error_code>, 'message' : <error_message> }  
}  
where:  
  <request_id> : Request id number from the request which produced this result  
  <error_code> : Error code for exception  
  <error_message> : Error message for exception
```

## 2.2 Supported Methods

### 2.2.1 Camera

**get\_camera\_info:** Accepts:

Nothing.

Returns:

```
{ 'result' : {
    'binning' : <binning>,
    'framesize' : <framesize>,
    'roi' : <roi>
  }
}
where:
  <binning> : (Integer) Camera binning
  <framesize> : (List) (Camera width, Camera Height)
  <roi> : (List) (Leftmost X, Uppermost Y, Width, Height)
```

**get\_camera\_x\_pixelsize:** Accepts:

Nothing.

Returns:

```
{ 'result' : {
    'get_camera_x_pixelsize' : <size>
  }
}
where:
  <size> : (Float) Camera pixel X size in microns
```

**get\_camera\_y\_pixelsize:** Accepts:

Nothing.

Returns:

```
{ 'result' : {
    'get_camera_y_pixelsize' : <size>
  }
}
where:
  <size> : (Float) Camera pixel Y size in microns
```

**get\_camera\_max\_binning:** Accepts:

Nothing.

Returns:

```
{ 'result' : {
    'get_camera_max_binning' : <maxbin>
  }
}
```

(continues on next page)



(continued from previous page)

```

}
where:
    <maxbin> : (Integer) Maximum binning supported

```

**get\_camera\_egain:** Accepts:

```
Nothing.
```

**Returns:**

```

{ 'result' : {
    'get_camera_egain' : <egain>
  }
}
where:
    <egain> : (Float) Camera gain in electrons/ADU

```

**get\_camera\_gain:** Accepts:

```
Nothing.
```

**Returns:**

```

{ 'result' : {
    'get_camera_gain' : <gain>
  }
}
where:
    <gain> : (Float) Camera gain

```

**get\_current\_temperature:** Accepts:

```
Nothing.
```

**Returns:**

```

{ 'result' : {
    'current_temperature' : <curtemp>
  }
}
where:
    <curtemp> : (Float) Current camera temperature

```

**get\_target\_temperature:** Accepts:

```
Nothing.
```

**Returns:**

```

{ 'result' : {
    'get_target_temperature' : <targetemp>
  }
}
where:
    <targetemp> : (Float) Current camera target temperature

```

**set\_target\_temperature:** Accepts:

```
{
  'target_temperature' : <temperature>
}
where:
  <temperature> : (Float) Target cooler temperature
```

Returns:

```
{
  'complete' : true,
}
```

**get\_cooler\_state:** Accepts:

Nothing.

Returns:

```
{ 'result' : {
    'get_cooler_state' : <state>
  }
}
where:
  <state> : (Boolean) Whether cooler is on (True) or off (False)
```

**get\_cooler\_power:** Accepts:

Nothing.

Returns:

```
{ 'result' : {
    'get_cooler_power' : <power>
  }
}
where:
  <power> : (Float) Current camera cooler power level
```

**set\_cooler\_state:** Accepts:

```
{
  'cooler_state' : <state>
}
where:
  <state> : (Boolean) Whether cooler is on (true) or off (false)
```

Returns:

```
{
  'complete' : true,
}
```

**take\_image:** Accepts:

```
{
  'exposure' : <exposure>,
  'binning' : <binning>,
}
```

(continues on next page)

(continued from previous page)

```

    'roi' : <roi>,
    'frametype' : <frametype>
}
where:
    <exposure> : (Float) Exposure time in seconds
    <binning> : (Integer) Camera binning
    <roi> : (List) ROI for exposure - (Leftmost X, Uppermost Y, Width, Height)
    <frametype> : (String) 'Light', 'Dark', 'Bias', or 'Flat **NOTE** Only 'Light'
↳supported!

```

**Returns:**

```

{
    'complete' : true,
}

```

**save\_image:** Accepts:

```

{
    'filename' : <filename>
}
where:
    <filename> : (String) Output filename including path if required

```

**Returns:**

```

{
    'complete' : true,
}

```

## 2.2.2 Focuser

**focuser\_get\_absolute\_position:** Accepts:

```

Nothing.

```

**Returns:**

```

{ 'result' : {
    'focuser_get_absolute_position' : <position>
}
}
where:
    <position> : (Integer) Focuser absolute position

```

**focuser\_get\_max\_absolute\_position:** Accepts:

```

Nothing.

```

**Returns:**

```

{ 'result' : {
    'focuser_get_max_absolute_position' : <max_position>
}
}

```

(continues on next page)

(continued from previous page)

```
where:
    <max_position> : (Integer) Maximum allowed absolute position
```

**focuser\_get\_current\_temperature:** Accepts:

```
Nothing.
```

Returns:

```
{ 'result' : {
    'focuser_get_current_temperature' : <curtemp>
  }
}
where:
    <curtemp> : (Float) Current focuser sensor temperature
```

**focuser\_is\_moving:** Accepts:

```
Nothing.
```

Returns:

```
{ 'result' : {
    'focuser_is_moving' : <moving>
  }
}
where:
    <moving> : (Boolean) Whether focuser is currently moving or not
```

**focuser\_stop:**

**Accepts:** :: Nothing.

Returns:

```
{ 'result' : {
    'stop' : <result>
  }
}
where:
    <result> : (Boolean) Success or not
```

**focuser\_move\_absolute\_position:** Accepts:

```
{
    'absolute_position' : <position>
}
where:
    <position> : (Integer) Absolute position to move focuser to
```

Returns:

```
{
    'complete' : true,
}
```

## INDICES AND TABLES

- `genindex`
- `modindex`
- `search`